



DoubleTime[®] 9.5

Standalone & Workstation Server

Installation Guide

DoubleTime® 9.5

Installation Guide



Table of Contents

Minimum System Requirements.....	3
Preparing to Install/Upgrade DoubleTime®.....	4
Installing the Stand-Alone version of DoubleTime – Full Install.....	5
Upgrading the Stand Alone or Network Client version of DoubleTime.....	8
Installing the Windows Workstation Server/Client (PTP) – Full Install.....	13
Installing the Windows Dedicated Server (NT) – Server Install	17
Installing the Windows Dedicated Client (NT) – Client Application	23
Upgrading the Windows Workstation Server (PTP/NT).....	27
DoubleTime® Database Upgrade Tool.....	31



DoubleTime® 9.5

Installation Guide



Minimum System Requirements

Desktop/Laptop Operating Systems:

- Microsoft Windows 11 64-bit
- Microsoft Windows 10 32-bit or 64-bit (End of Support October 14, 2025)

Note: Network users of DoubleTime must maintain a wired local area connection to the DoubleTime database. In a network environment, please upgrade the server prior to upgrading client PCs. Note that DoubleTime 9.5 requires administrator access to the server to perform the upgrade.

Server Operating System:

- Windows Server™ 2019

Minimum Hardware for Desktop / Laptop Devices:

- 1 GHz Processor
- 4 GB RAM (8 GB RAM recommended)
- 500 MB free disk space for client files and at least three times (3X) the size of the database
- 256 MB Video Card Recommended

Bandwidth:

- High-speed Internet connectivity

Recommended Browsers:

- Chrome, Firefox, Microsoft Edge

Additional Requirements:

**Minimum Requirements are subject to change and are not guaranteed to support future products made available by The Fund.*

- Microsoft .NET Framework 4.8
- PDF Reader

Additional Recommendations:

- Uninterrupted Power Supply (UPS)
- Back-up solution for data
- Anti-Virus/Anti-Spyware Protection
- Firewall



DoubleTime® 9.5

Installation Guide



Preparing to Install/Upgrade DoubleTime®

- Please read the following instructions *thoroughly* before starting the install/upgrade.
- Log on to the PC with Administrative Rights before attempting to install/upgrade DoubleTime.

Note: During the install process, you may experience multiple User Access Control prompts requesting permission to continue.

- Verify PC meets the minimum hardware/software requirements listed above.
- Verify there is sufficient free hard drive space on the PC to accommodate backing up the production database (at least 3X) and 500MB for the install.
- Prior to upgrading, create a backup of the current database via **Utilities | Database Backup** in DoubleTime.
- Turn off or disable any anti-virus or anti-spyware/malware programs.

For any questions regarding installation of this product, please call Member Support at [1-800-421-9378](tel:1-800-421-9378).



DoubleTime® 9.5

Installation Guide



Installing the Standalone version of DoubleTime – Full Install

1. Log on with Administrative Rights.
2. Close any programs currently running, including DoubleTime.
3. Download and run the DoubleTime 9.5 installation file obtained from the DoubleTime Support page located at <https://www.thefund.com>.
4. Click '**Next**' on the Installation Welcome window illustrated below:




DoubleTime® 9.5


Installation Guide



5. Choose **'Standalone'** and click the **'Next'** button.



6. The next window brings up the **'Destination Folder'** dialog. You can set the path where the application components are installed. It is recommended that you use the default installation path that is provided. Select **'Next'**.




DoubleTime® 9.5

Installation Guide



- Click the 'Install' button and DoubleTime will begin the installation process.



- Congratulations, DoubleTime is now installed. Click '**Finish**' to complete the installation. Launch DoubleTime from your desktop icon or from your start menu.



DoubleTime® 9.5

Installation Guide



Upgrading the Standalone or Network Client version of DoubleTime

1. Log on with Administration Rights
2. Make a backup of the current production database:
 - a. Create a folder on your PC (i.e., [c:\DTbackup](#)).
 - b. Open the DoubleTime application.
 - c. Select **Utilities | Database Backup**
 - d. Select the directory you created (i.e., [c:\DTbackup](#)).
 - e. Click the 'OK' button.
3. Close any programs currently running, including DoubleTime.
4. Download and run the DoubleTime 9.5 installation file obtained from the DoubleTime Support page on <https://www.thefund.com>.




DoubleTime® 9.5


Installation Guide



5. Click **'Next'** on the Installation Welcome window illustrated below:




6. Click the **'Install'** button and DoubleTime will begin the installation process.




7. Click **'OK'** on the DoubleTime 9.5 Installer Information prompt to allow the installation to continue.

DoubleTime® 9.5

Installation Guide



5. Congratulations, DoubleTime is now upgraded. Click '**Finish**' to complete the installation.



6. Upgrade the DoubleTime database by launching DoubleTime your desktop icon or from your start menu.




DoubleTime® 9.5

Installation Guide



7. DoubleTime will automatically recognize that the database requires an upgrade and present the following message:



8. Click 'OK' to close the message and launch the DoubleTime® Database Upgrade tool. Note that this must be run with Administrator privileges.

See **DoubleTime® Database Upgrade Tool** below for more information.

Note: If this is a Network Client upgrade, the Database Upgrade tool will prevent you from continuing. At this point, upgrade the server and then proceed with step 12.


See **Upgrading the Windows Workstation Server (PTP/NT)** below for more information.

DoubleTime® 9.5

Installation Guide



12. Upgrade the DoubleTime database software by launching DoubleTime your desktop icon or from your start menu. Once the upgrade completes, DoubleTime can be launched and will now be updated completely.




DoubleTime® 9.5

Installation Guide



Installing the Windows Workstation Server/Client (PTP) – Full Install

1. Log on with Administrative Rights.
2. Close any programs currently running, including DoubleTime.
3. Download and run the DoubleTime 9.5 installation file obtained from the DoubleTime Support page on www.thefund.com.
4. Click '**Next**' on the Installation Welcome window illustrated below:
5. Choose '**Network**' and click the '**Next**' button.
6. The next window brings up the '**Network Type**' dialog. Select the check box for '**Client**' and then the option for '**Windows Workstation Server (PTP)**'.
7. If this machine will function as the database server also check '**Server**' and then select '**Windows Workstation Server (PTP)**'.



Note: Only one server installation should be selected per office. When installing additional PTP clients, only select the '**Client**' checkbox along with the Windows Workstation Server (PTP) radio button.

DoubleTime® 9.5

Installation Guide




8. When you are finished with your selection, click 'Next'.

DoubleTime® 9.5


Installation Guide



9. The next window presents the 'Destination Folder' dialog. The first selection will set the path for the server application files. The second selection will set the path for the DoubleTime database files. Select 'Next'.



10. Click the 'Install' button and DoubleTime will begin the installation process.




DoubleTime® 9.5

Installation Guide



11. Congratulations, DoubleTime is now installed. Click '**Finish**' to complete the installation. Launch DoubleTime from your desktop icon or from your start menu.



12. **Note:** Refer to steps 1-6 for installing additional clients.

DoubleTime® 9.5

Installation Guide



Installing the Windows Dedicated Server (NT) – Server Install

Note: The installation instructions illustrated below will only install the database files.

1. Log on with Administrative Rights.
2. Close any programs currently running, including DoubleTime.
3. Download and run the DoubleTime 9.5 installation file obtained from the DoubleTime Support page on www.thefund.com.
4. Click '**Next**' on the Installation Welcome window illustrated below:




DoubleTime® 9.5

Installation Guide



5. Choose '**Network**' and click the '**Next**' button.



6. The next window brings up the '**Network Type**' dialog. Select the check box for **Server** and the radio button for '**Windows Dedicated Server (NT)**'.

Note: Only one server installation should be selected per office.

DoubleTime® 9.5

Installation Guide



7. When you are finished with your selection, click **'Next'**.


8. The next window brings up the **'Password'** dialog. Enter the password provided from the order information supplied at purchase. Select **'Next'**.

DoubleTime® 9.5


Installation Guide



9. Enter this server’s IP address as it will host the DoubleTime database.



10. The next window presents the ‘**Destination Folder**’ dialog. The first selection will set the path for the server application files. The second selection will set the path for the DoubleTime database files. Select ‘**Next**’.




DoubleTime® 9.5

Installation Guide



11. Click the **'Install'** button and DoubleTime will begin the installation process.



12. Congratulations, the DoubleTime Database Service and files are installed and configured. Click **'Finish'** to complete the installation.



Note: There will not be any icons installed but if you would like to confirm a proper installation, please search the running services for “DoubleTime Database Service.”

DoubleTime® 9.5

Installation Guide



Note: If Windows Firewall is active on the server, you will need to add **dbsrv17.exe** as an exception. This will allow the clients PCs to connect through TCPIP.



DoubleTime® 9.5

Installation Guide



Installing the Windows Dedicated Client (NT) – Client Application

Note: The installation instructions illustrated below will only install the client application and cannot be used without the server files installed.

1. Log on with Administrative Rights.
2. Close any programs currently running, including DoubleTime.
3. Download and run the DoubleTime 9.5 installation file obtained from the DoubleTime Support page on www.thefund.com.
4. Click '**Next**' on the Installation Welcome window illustrated below:




DoubleTime® 9.5


Installation Guide



5. Choose **'Network'** and click the **'Next'** button.



6. The next window brings up the **'Network Type'** dialog. Select the check box for *Client* and the radio button for **'Windows Dedicated Server (NT)'**.
7. When you are finished with your selection, click **'Next'**.



DoubleTime® 9.5


Installation Guide



8. Enter the IP address of the server that is hosting the DoubleTime database.



9. The next window brings up the '**Destination Folder**' dialog. You can set the path where the Client application components are installed. It is recommended that you use the default installation path that is provided. Select '**Next**'.




DoubleTime® 9.5

Installation Guide



10. Click the 'Install' button and DoubleTime will begin the installation process.



11. Congratulations, DoubleTime is now upgraded. Click 'Finish' to complete the installation.



DoubleTime® 9.5

Installation Guide



Upgrading the Windows Workstation Server (PTP/NT)

1. Log on with Administration Rights
2. Make a backup of the current production database:
 - a. Create a folder on your PC (i.e., [c:\DTbackup](#)).
 - b. Open the DoubleTime application.
 - c. Select **Utilities | Database Backup**
 - d. Select the directory you created (i.e., [c:\DTbackup](#)).
 - e. Click the 'OK' button.
3. Close any programs currently running, including DoubleTime.
4. Download and run the DoubleTime 9.5 installation file obtained from the DoubleTime Support page on <https://www.thefund.com>.



DoubleTime® 9.5


Installation Guide



- Click **'Next'** on the Installation Welcome window illustrated below:



- Click the **'Install'** button and DoubleTime will begin the installation process.




DoubleTime® 9.5


Installation Guide



- Click 'OK' on the DoubleTime 9.5 Installer Information prompt to allow the installation to continue.



- Congratulations, DoubleTime is now upgraded. Click 'Finish' to complete the installation.



- DoubleTime will automatically recognize that the database requires an upgrade and launch the DoubleTime® Database Upgrade tool. Note that this must be run with Administrator privileges.

See **DoubleTime® Database Upgrade Tool** below for more information.

DoubleTime® 9.5


Installation Guide



10. Upgrade the DoubleTime database software by launching DoubleTime your desktop icon or from your operating system start menu. Once the upgrade completes, DoubleTime can be launched and will now be updated completely.

Note: If this installation does not have the DoubleTime client files installed, perform this step as part of a client upgrade.

See **Upgrading the Standalone or Network Client** version of DoubleTime above for more information.




DoubleTime® 9.5

Installation Guide



DoubleTime® Database Upgrade Tool

1. Log on with Administrative Rights.
2. Close any programs currently running, including DoubleTime.
3. If the Database Upgrade tool does not open automatically, navigate to the directory where DoubleTime is installed (typically [C:\Program Files \(x86\)\The Fund\DoubleTime](#)) and double click on **dt_sa17_db_upgrade.exe**.
4. Click '**Next**' on the Welcome window illustrated below:



DoubleTime® 9.5

Installation Guide



5. Via the drop down, select the database to upgrade (note there is typically only one option in the list) and click **'Next'**.

DoubleTime® Database Upgrade

DT DOUBLETIME

Welcome

- Select Database**
- Database Backup
- Perform Upgrade
- Finish

Select Database

Choose database to upgrade:

DoubleTime

Server Connections	Database Size	Estimated Time to Complete
1	164 MB	6 Min

Refresh

Details

Connection Description: DoubleTime Database

Connection Type: STANDALONE

Database Driver: SQL Anywhere 17

Engine Name: Dbtime

Network Protocol: TCP/IP()

Database Name: Dbtime

Database File: C:\ProgramData\The Fund\DoubleTime\dbtime.db

Cancel Previous Next

Note: Based on the size of the database selected to be upgraded, the tool makes an estimate of the time it will take to complete. Please also note that:


- The actual time may vary widely based on system configuration.
- All connections to the database will be closed during this operation. If “Server Connections” reflects more than 1, it indicates there may be other clients currently using this database. It is advisable to find and close all other connections rather than forcibly disconnecting via this tool.

DoubleTime® 9.5

Installation Guide



6. Select or enter a directory to back up the database into and click 'Make backup.' Once the backup has completed successfully, the tool will automatically move to the next step. If not, click 'Next' to continue.




DoubleTime® 9.5

Installation Guide



7. By default, the upgrade will begin automatically. If not, click '**Start Upgrade**' to perform the upgrade. Once the upgrade has completed successfully, the tool will automatically move to the final step. If not, click '**Next**' to continue.




Note: This process generally has frequent pauses where it appears no progress is being made. This is normal and is not cause for concern. Please be patient and reach out to Member Support if you have any questions or concerns.

DoubleTime® 9.5

Installation Guide



8. Click 'Finish' to close the Database Upgrade tool.



Note: Update existing scheduled tasks that use SQL Anywhere 11 utilities (such as database backup) to use the new SQL Anywhere 17 utilities. Contact Member Support for more information.



DoubleTime[®]9.5

For additional assistance with DoubleTime
please visit www.thefund.com

